readme.md 10/30/2020

# Python script for downloading time recordings for all devices within a spefic time range

There are two main scripts:

- download\_recordings.py
- download\_recordings\_tdms.py

Script 1: download\_recordings.py

**download\_recordings.py** is an example of an python script for automatated download and delete of time recordings. The time recording data is returned in json format one channel at a time

- 1. The script will logon to pchcloud or local server.
- 2. Query for devices
- 3. For each device it will query for any recordings within a time range (default is the last day). If any then download and (optionally) delete the recoding on the server

Script 2: download\_recordings\_tdms.py

**download\_recordings\_tdms.py** is an example of an python script for automatated download in *National Intstrument tdms* format, save, and delete of time recordings.

The downloaded files are saved on the local disk in the path specified by the "download\_path" in the config.json

- 1. The script will logon to pchcloud or local server.
- 2. Query for devices
- 3. For each device it will query for any recordings within a time range (default is the last day). If any then download in *tdms* format, save the file and (optionally) delete the recoding on the server

### Install

The installation steps may be different on different platforms. However the basic priciple is the same.

1. Create virtual environment

py -m venv env

2. Activate virtual environment

.\env\Scripts\activate

10/30/2020 readme.md

3. Install requirements listed in requirements.txt

```
pip3 install -r requirements.txt
```

or if using python3.8 use

```
pip3 install -r requirements3_8.txt
```

## Setting up

In order for the script to run - 2 files are required. The files must be locatated in the same folder as the script

1. **hosts.json** for setting up urls to backend-services

```
{
    "pchcloud": {
        "backend": "https://pchcloud.pch-engineering.dk/backend",
        "usermanager": "https://pchcloud.pch-engineering.dk/usermanager",
        "devicemanager": "https://pchcloud.pch-engineering.dk/devicemanager"
   },
    "local": {
        "backend": "http://localhost:5000/api",
        "usermanager": "http://localhost:5020/api",
        "devicemanager": "http://localhost:5030/api"
   },
}
```

The example has two known hosts.

- o "pchcloud" can be used if the data is download from https://pchcloud.pch-engineering.dk
- "local" can be used if the backend-services are running on the same pc as the script is executed.

More hosts can be added by inserting a new section, for example

```
"mypc": {
      "backend": "http://192.168.1.105:5000/api",
       "usermanager": "http://192.168.1.105:5020/api",
      "devicemanager": "http://192.168.1.105:5030/api"
  },
```

To the **host.json** 

readme.md 10/30/2020

```
"pchcloud": {
       "backend": "https://pchcloud.pch-engineering.dk/backend",
       "usermanager": "https://pchcloud.pch-engineering.dk/usermanager",
       "devicemanager": "https://pchcloud.pch-engineering.dk/devicemanager"
   },
   "local": {
       "backend": "http://localhost:5000/api",
       "usermanager": "http://localhost:5020/api",
       "devicemanager": "http://localhost:5030/api"
   },
   "mypc": {
       "backend": "http://192.168.1.105:5000/api",
       "usermanager": "http://192.168.1.105:5020/api",
       "devicemanager": "http://192.168.1.105:5030/api"
   },
   "pchedge": {
       "backend": "https://172.19.1.181/backend",
       "usermanager": "https://172.19.1.181/usermanager",
       "devicemanager": "https://172.19.1.181/devicemanager"
   },
}
```

This can be usefull is the backend-services is running on another pc.

#### 2. **config.json** is for configurtion settings

```
{
    "host":"local",
    "username": "local",
    "password": "pass",
    "delete_on_server": false,
    "query_passed_days": 1,
    "download_path":"downloads"
}
```

- "host" sets the server connections from the list of known hosts in the \*hosts.json file
- "username" and "password" is the account login. If connecting to local the default username is 'local' and the password is 'pass'
- o "delete\_on\_server", if true recordings WILL BE DELETED on the server
- "query\_passed\_days", query time range number of days back from current time
- "query\_passed\_days", query time range number of days back from current time
- o "download\_path", local download path, currently used by the download\_recordings\_tdms.py

## Execute python script

readme.md 10/30/2020

or

py ./download\_recordings\_tdms.py